# How to Stream Realtime to LiveLitigation

- Court reporter instructions for setting up CAT software and streaming realtime to LiveLitigation.
- Perform the steps below on your CAT computer.
- Go to https://www.livelitigation.com/
    - Hover over Support and click on Downloads



    - Click on the Download link for RealtimeDirect



    - Open RealtimeDirect.zip
        - Follow the prompts on your screen to unzip the file.
    - Double click on the .msi file.
        - Type: Windows Installer Package
        - "Windows protected your PC"
            - Click on More info, then Run anyway



- Follow the prompts on your screen to finish installing RealtimeDirect. Once installed, the icon for RealtimeDirect will be on your desktop.

# Protocol and COM Port Settings

- Select either Bridge or Caseview
  - Eclipse, DigitalCAT, and other CAT systems that can use the Bridge protocol and output using the baud rate 38,400 should choose Bridge.
  - CaseCAT and other systems limited to the Caseview protocol should choose Caseview.



- Check Open COM Port Automatically to save your protocol setting and open the virtual COM port in the future.
  - This step is only necessary for first-time setup.
- Click on Open COM
  - "COM Port 41 has been Opened"
- Enter the 12-digit key from your email invitation and click Submit

# CAT Software Settings

- Open your CAT Software
  - If you have performed the installation steps above and had your CAT software open, please close and reopen your CAT software.
- Configure your output settings for COM 41:
  - Eclipse and other Bridge Protocol users:
    - Open your User Settings.
    - Go to the Realtime tab.
    - Click on the Add button.
    - Choose Bridge as the Output.
      - Make sure that "Apply Edits" is checked.
    - Select COM port and click Setup.
    - On the new window that opens, choose COM 41 as the port.
    - Make sure the baud rate is 38k or 38,400.
    - Click Ok on the COM port setup window.
    - Click Ok on the Output format window.
    - Start a realtime file.
  - CaseCatalyst and other Caseview Protocol users:
    - Go to your Translate window.
    - Double check that your Output To: drop down menu is set to Caseview.
    - Click on Options and then to your Output CaseView tab.
    - Check Output over comm port.
    - Select COM41 from the list.
    - Make sure that Direct (Cable) is select.
      - The virtual COM port connection that LiveLitigation makes is read as a physical cable plugged into the reporter's computer.
    - Click Ok on the Case CATalyst Translate Options Window.
    - Start a realtime file.

# Data and Clear Steno

- Check the Data I/O to see if your COM port is setup properly
- Click Clear Steno to delete realtime that was previously-sent.

# Joining the Event

- Click the link in your email invitation.

**LiveLitigation**

## Meeting Name:
Test Invitation Example

## Date / Time:
Thu Mar 18 2021 6:15 AM (PDT/UTC-07:00)

## Conference Call:
Call In: US +1 (206) 928-9280

Conference ID: 6653121

## Host:
LiveLitigation

## Your Key:
vuhzji041335

Join Meeting

Not working? Copy and paste the following link into your browser:

https://demo.livelitigation.com/meeting/?key=vuhzji041335

- Enter your name and click Join.

**Join Now**

Test Invitation Example ✔

CSR Invite

I agree to be bound by the terms of the Privacy Policy and End User License Agreement.

https://livelitigation.com/eula.html

Join

- Allow your Camera.
- Allow your microphone.
- Choose Computer to use your computer hardware and webcam.
  - Also use this option if you have external hardware connected to your computer.
  - Choosing Phone mutes incoming audio (you can't hear anyone).
  - Choosing Phone also prevents you from turning on your microphone (you can't talk).
- Preview your camera, microphone, and speakers on the next page.
- Click Join Now to join the event.



- Upon connecting, you will be able to see the transcript.